



Wendy Craft Cotton

Hearty Bib

Photographed in: Wendy Craft Cotton: 2 colours used: #2007 & 2002;
3 colours used: #2002, 2003 & 2004

MATERIALS AND MEASUREMENTS		
Width approx	20 8	cm ins
Length of main section approx	18 7	cm ins
Total length incl straps approx	29 11 ½	cm ins
Wendy Craft Cotton (100gr)		
2 colours used:		
#2007 (A) + #2002 (B)	1 ball each	
3 Colours used version 1:		
#2002 (A) + #2003 (B) + #2004 (C)	1 ball each	
3 Colours used version 2:		
#2003 (A) + #2004 (B) + #2002 (C)	1 ball each	
Needle sizes	4.5mm (US 7) straight needles 1 button	
Incomparable Buttons	L194	

The quantities of yarn stated are based on average requirements and are therefore approximate. The brand Naturally owns the copyright for this pattern. No part of this pattern may be reproduced, transmitted in any form or by any means, electronic, mechanical, photocopying, recording, or otherwise without permission in writing. © Naturally

ABBREVIATIONS
Beg - beginning
cm - centimetres
cont - continue
dec - decrease
ins - inches
k - knit
meas - measures
NR - next row
p - purl
patt - pattern
rem - remaining
rep - repeat
RS(F) - right side facing
st(s) - stitch(es)
Stst - Stocking stitch
tog - together
WS(F) - wrong side (facing)

M1k - pick up strand between last st worked and next st from back to front onto left hand needle and k it through the front loop
skp - slip 1 stitch, knit 1 stitch, pass the slipped stitch over;

IMPORTANT
Use ONLY the yarn specified. (We cannot accept responsibility for an imperfect garment if any other brand is used.)

TENSION
19 sts and 24 rows over Stst - 10cm x 10cm/4ins x 4ins on 4.5mm (US 7) needles.

CHECK YOUR TENSION CAREFULLY

NOTE: The 2 colour version makes 2 bibs. The 3 colour version makes 3 bibs if shades are swapped with each other.

BIB
Using 4.5mm and A, cast on 39 sts. Garter Stitch (= k every row) for 3 rows.

NR (RS) - K24, turn, (leave rem 15 sts unworked).

NR (WS) - Slip 1 purlwise, p8, turn, (leave rem 15 sts unworked).

NR (RS) - Slip 1 knitwise, k13, turn, (leave rem 10 sts unworked).

NR (WS) - Slip 1 purlwise, p18, turn, (leave rem 10 sts unworked).

NR (RS) - Slip 1 knitwise, k23,

turn, (leave rem 5 sts unworked).
NR (WS) - Slip 1 purlwise, p28, turn, (leave rem 5 sts unworked).
NR (RS) - Slip 1 knitwise, k33.
NR (WS) - K3, p33, k3.
NR (RS) - K39.
NR (WS) - K3, p33, k3.
Begin Heart Motif
 This section is written for the 2 colour version with the third colour for 3 colour version in ().
NR (RS) - A k10; B k19; A k10.
NR (WS) - A k3, p7; B p19; A p7, k3.
 Rep last 2 rows once more.
NR (RS) - A k10; B k9; A (C) k1; B k9; A k10.
NR (WS) - A k3, p7; B p8; A (C) p3; B p8; A p7, k3.
NR (RS) - A k10; B k8; A (C) k3; B k8; A k10.
NR (WS) - A k3, p7; B p7; A (C) p5; B p7; A p7, k3.
NR (RS) - A k10; B k7; A (C) k5; B k7; A k10.
NR (WS) - A k3, p7; B p6; A (C) p7; B p6; A p7, k3.
NR (RS) - A k10; B k6; A (C) k7; B k6; A k10.
NR (WS) - A k3, p7; B p5; A (C) p9; B p5; A p7, k3.
NR (RS) - A k10; B k5; A (C) k9; B k5; A k10.
NR (WS) - A k3, p7; B p4; A (C) p11; B p4; A p7, k3.
NR (RS) - A k10; B k4; A (C) k11; B k4; A k10.
NR (WS) - A k3, p7; B p3; A (C) p13; B p3; A p7, k3.
NR (RS) - A k10; B k3; A (C) k13; B k3; A k10.
NR (WS) - A k3, p7; B p3; A (C) p13; B p3; A p7, k3.
NR (RS) - A k10; B k3; A (C) k6; B k1; A (C) k6; B k3; A k10.
NR (WS) - A k3, p7; B p3; A (C) p5; B p3; A (C) p5; B p3; A p7, k3.
NR (RS) - A k10; B k3; A (C) k4; B k5; A (C) k4; B k3; A k10.
NR (WS) - A k3, p7; B p4; A p2; B p7; A p2; B p4; A p7, k3.
NR (RS) - A k10; B k19; A k10.
NR (WS) - A k3, p7; B p19; A p7, k3.
 Rep last 2 rows once more.
 Continue from here using A only:
NR (RS) - A k39.
NR (WS) - A k3, p33, k3.
 Rep last 2 rows once more.
NR (RS) - K39.
NR (WS) - K3, p10, k13, p10, k3.

NR (RS) - K39.
NR (WS) - K3, p9, k15, p9, k3.
NR (RS) - K39.
NR (WS) - K3, p8, k17, p8, k3.
Shape Neck
NR (RS) - K14, cast off 11, k to end.
NR (WS) - K3, p8, k3. Leave rem 14 sts for opposite strap on hold)
NR (RS) - K3, skp, k9 - 13 sts.
NR (WS) - K3, p7, k3.
NR (RS) - K3, skp, k8 - 12 sts.
NR (WS) - K3, p6, k3.
NR (RS) - K3, skp, k7 - 11 sts.
NR (WS) - K3, p5, k3.
NR (RS) - K3, skp, k6 - 10 sts.
NR (WS) - K3, p4, k3.
NR (RS) - K10.
NR (WS) - K3, p4, k3.
 Rep last 2 rows 6 times more.
NR (RS) - K10.
NR (WS) - K4, p2, k4.
NR (RS) - K1, k into front and back of next st, k8 - 11 sts.
NR (WS) - K8, M1k, k3 - 12 sts.
NR (RS) - K1, k into front and back of next st, k10 - 13 sts.
NR (WS) - K12, M1k, k1 - 14 sts.
NR (RS) - K1, k into front and back of next st, k10, k2tog.
NR (WS) - K2tog, k11, M1k, k1.
 Rep last 2 rows once more.
NR (RS) - K1, k into front and back of next st, k10, k2tog.
NR (WS) - Cast off 6 sts, k to end - 8 sts.
NR (RS) - K1, k into front and back of next st, k4, k2tog - 8 sts.
NR (WS) - Cast off.
NR (WS) - Rejoin yarn to sts o hold; k3, p8, k3.
NR (RS) - K9, k2tog, k3 - 13 sts.
NR (WS) - K3, p7, k3.
NR (RS) - K8, k2tog, k3 - 12 sts.
NR (WS) - K3, p6, k3.
NR (RS) - K7, k2tog, k3 - 11 sts.
NR (WS) - K3, p5, k3.
NR (RS) - K6, k2tog, k3 - 10 sts.
NR (WS) - K3, p4, k3.
NR (RS) - K10.
NR (WS) - K3, p4, k3.
 Rep last 2 rows 6 times more.
NR (RS) - K10.
NR (WS) - K4, p2, k4.
NR (RS) - K8, k into front and back of next st, k1 - 11 sts.
NR (WS) - K3, M1k, k8 - 12 sts.
NR (RS) - K10, k into front and back of next st, k1 - 13 sts.
NR (WS) - K1, M1k, k12 - 14 sts.
NR (RS) - Skp, k10, k into front and back of next st, k1.

NR (WS) - K1, M1k, k11, k2tog. Rep last 2 rows twice more.
NR (RS) - Cast off 6 sts, k to end - 8 sts.
NR (WS) - K1, M1k, k5, k2tog - 8 sts.
NR (RS) - Cast off 6 sts - 2 sts. Garter Stitch (= k every row) on these 2 sts for 12 - 14 rows (depending on size of button to be used).
 Cast off.
 Join cast-off edge to middle of last 6-st-cast-off.
 Sew in ends.
 Sew on button.